



# Instruction Manual

Version 1.0 (09/2022)

Václav Nežerka and Michael Somr

FCE, CTU in Prague

[vaclav.nezerka@fsv.cvut.cz](mailto:vaclav.nezerka@fsv.cvut.cz), [michael.somr@fsv.cvut.cz](mailto:michael.somr@fsv.cvut.cz)

## Introduction

Free open-source software PyPIV (Python Particle Image Velocimetry) was designed to evaluate kinetic fields for granular media such as sand. The software was developed and tested with Python 3.6.

### 1. Program Structure

The program initiates after running the *PyPIV.py* file, located in the root program folder (Figure 1). It is recommended to put the analyzed images in the *imgs* folder. Exported data (images, text files) can be found in the “export” folder, while the project data and settings of the graphical user interface (GUI) are saved in the *saved\_projects* folder.




Figure 1: Structure of the program folders and files.

### 2. Running *PyPIV.py*

After running the PyPIV program, a simple GUI with all controls opens (Figure 2). The user is required to either create a new project (by importing images: *File -> Import Images*) or to load one, after which setting a region of interest (ROI), scaling, and analysis settings become available (Figure 3). Note that when drawing ROI, the left-mouse-button click adds a point of the ROI polygon, while the right-mouse-button click deletes the previous one, and pressing the ESC key saves the ROI (Figure 4). The calculation grid can be displayed by selecting the radio button *Grid* (Figure 5) and adjusted using the inputs for *Subset size* and *Subset spacing*.

Before running the analysis, it is recommended to scale the images (pixel-to-mm ratio) and set the analysis parameters (Figure 6): *Frame period* (how often the frames were taken during the experiment), *Subpixel accuracy* (precision of the correlation algorithm), *Backward analysis [yes/no]* (the last image in the sequence becomes reference), and *Update subset position [yes/no]* (whether the subsets follow the displacements (suitable for large displacements) or stay at a fixed location during the analysis (to avoid the potential accumulation of errors)). The results can be viewed for each image in the sequence in the form of a *Quiver plot*, a *Contour plot* for horizontal and vertical velocity components, and a deformed grid by selecting the *Subsets* radio button (Figure 7).




Figure 2: GUI of PyPIV after running the program.




Figure 3: GUI of PyPIV after loading the images.




Figure 4: Selected ROI for calculation of kinetic fields.




Figure 5: Displaying the calculation grid.




Figure 6: Setting of analysis parameters.




Figure 7: Displaying results.

## **Acknowledgment**

Financial support by the grant SGS22/029/OHK1/1T/11, provided by the Faculty of Civil Engineering at CTU in Prague is gratefully acknowledged.